
gcmfaces

a Matlab framework for the analysis of gridded earth variables



Gäel Forget

Dept. of Earth, Atmospheric and Planetary Sciences Massachusetts Institute of Technology Cambridge MA 02139 USA

May 23, 2016

Contents

1	1 Download And Update					
	1.1	download frozen copies	3			
	1.2	use the MITgcm CVS server	3			
	1.3	getting started with gcmfaces	4			
2	The	e gcmfaces class	7			
3 Basic Features						
	3.1	Grid Variables	10			
	3.2	Exchange Functions	12			
	3.3	Overloaded Functions	12			
	3.4	I/O Functions	13			
4	Tut	orial	14			
5	Standard Analysis					

Summary

gcmfaces is a Matlab toolbox designed to handle gridded earth variables; results of MITgcm ocean simulations originally (Forget et al., 2015). It allows users to seamlessly deal with various gridding approaches (e.g. see Fig. 2) using compact and generic codes. It includes many basic and more evolved functionalities such as plotting global maps, computing transports, and budgets. MITprof is a complementary toolbox designed to handle in-situ ocean observations (Forget et al., 2015). This document provides guidelines to download, update, and activate the software (section 1), documents basic design and features of gcmfaces (sections 2 and 3), and briefly describes higher level gcmfaces functionalities (sections 4 and 5).

References

- Forget, G., J.-M. Campin, P. Heimbach, C. N. Hill, R. M. Ponte, and C. Wunsch, 2015: ECCO version 4: an integrated framework for nonlinear inverse modeling and global ocean state estimation. *Geoscientific Model Development*, 8 (10), 3071–3104, doi:10.5194/gmd-8-3071-2015, URL http://www.geosci-model-dev.net/8/3071/2015/.
- Forget, G., J.-M. Campin, P. Heimbach, C. N. Hill, R. M. Ponte, and C. Wunsch, 2016: ECCO version 4: Second release. URL http://hdl.handle.net/1721.1/102062.

Disclaimer

Users of the gcmfaces software are kindly asked to include a reference to Forget et al. (2015) when publishing results that rely on gcmfaces. The free software programs may be freely distributed, provided that no charge is levied, and that the disclaimer below is always attached to it. The programs are provided as is without any guarantees or warranty. Although the authors have attempted to find and correct any bugs in the free software programs, the authors are not responsible for any damage or losses of any kind caused by the use or misuse of the programs. The authors are under no obligation to provide support, service, corrections, or upgrades to the free software programs.

¹ 1 Download And Update

² There are currently two ways to download gcmfaces and MITprof:

- 1. download frozen copies: arguably the simplest method that will work
 in all common computing environments (Linux, iOS, MS-windows).
- ⁵ 2. use the MITgcm CVS server: this is the recommended method under
 ⁶ Linux and iOS (assuming CVS was installed) since it has the major
 ⁷ advantage that the codes can later easily be updated.
- ⁸ This section documents both methods and the activation of gcmfaces.

⁹ 1.1 download frozen copies

- ¹⁰ Frozen copies of gcmfaces and MITprof are available at
- 11 ftp://mit.ecco-group.org/ecco_for_las/version_4/checkpoints/
- Download the latest versions¹, uncompress and untar them. Then add these two toolboxes to your Matlab path as explained in section 1.3.

¹⁴ 1.2 use the MITgcm CVS server

Login to the MITgcm CVS server as explained in this page² then download
the up to date versions of gcmfaces and MITprof by typing

```
17 cvs co -P -d gcmfaces MITgcm_contrib/gael/matlab_class
```

```
18 cvs co -P -d MITprof MITgcm_contrib/gael/profilesMatlabProcessing
```

All past and future evolutions of the codes can be traced using the **cvs** version control system. To update an existing copy of the codes and take advan-

tage of the latest developments one goes inside a directory and types 'cvs up-

¹c65w_gcmfaces.tar.gz and c65w_MITprof.tar.gz at the time of writing. ²http://mitgcm.org/public/using_cvs.html

date -P -d' at the command line. If you are new to cvs then you may want to
read about the update command at http://mitgcm.org/public/using_cvs.html.

²⁴ 1.3 getting started with gcmfaces

²⁵ Download toolboxes as explained above and the LLC90 grid (see Forget et al.,
²⁶ 2015) directory from this location³, organize directories as depicted in Fig. 1,
²⁷ start Matlab, go to the root directory indicated as './' in Fig. 1, and type:

```
%add gcmfaces and MITprof directories to Matlab path:
28
  p = genpath('gcmfaces/'); addpath(p);
29
  p = genpath('MITprof/'); addpath(p);
30
31
  %load nctiles_grid in memory:
32
  grid_load;
33
34
  %displays list of grid variables:
35
  gcmfaces_global; disp(mygrid);
36
```

The applications in sections 4 and 5 further require downloading model output from the ECCO version 4, release 2 ocean state estimate (Forget et al.,

³⁹ 2016) from ftp://mit.ecco-group.org/ecco_for_las/version_4/release2/ (see Fig. 1

 $_{40}$ caption for more detail) and the m_map plotting toolbox from

41 https://www.eoas.ubc.ca/~rich/map.html.

 $^{{}^{3}\}mathrm{ftp://mit.ecco-group.org/ecco_for_las/version_4/release2/nctiles_grid/}$

Figure 1: Directory structure that allows users to execute Matlab code snippets provided in this document. The most basic gcmfaces installation only requires the 'gcmfaces/', 'MITprof/', and 'nctiles_grid/' directories (see section 1 for details). The 'm_map' toolbox is frequently used for geographic depictions. The 'release2_climatology/', and 'release2/' directories serve to demonstrate higher-level functions in sections 4 and 5. Their contents are available at ftp://mit.ecco-group.org/ecco_for_las/version_4/release2/. The 'nctiles_monthly/' directory (170G) in particular contains the 1992-2011 monthly time series that, along with the 'nctiles_remotesensing/' and 'profiles/' (model-data misfits), allows users to reproduce the 'standard analysis' in Forget et al. (2016). The 'nctiles_climatology/' directory (10G) provides a light-weight alternative (Sect. 5).

```
/
__gcmfaces/ (Matlab toolbox)
__MITprof/ (Matlab toolbox)
__m_map/ (Matlab toolbox)
__nctiles_grid/ (netcdf files)
__release2_climatology/
__nctiles_climatology/
__mat/ (see section 5)
__tex/ (see section 5)
__release2/
__nctiles_monthly/
__nctiles_remotesensing/)
__profiles/
__mat/ (see section 5)
__tex/ (see section 5)
__tex/ (see section 5)
```




Figure 2: Four different ways of gridding the earth. Top left: lat-lon grid, mapping the earth to a single rectangular array ('face'). Top right: cubesphere grid, mapping the earth to the six faces of a cube. Bottom right: lat-lon-cap 'LLC' grid (five faces). Bottom left: quadripolar grid (four faces). Faces are color-coded, and the ocean topography underlaid. Only a subset of the grid lines are shown in this depiction, which furthermore artificially shows gaps between faces to magnify face edges.

⁴² 2 The gcmfaces class

The basic motivation for developing gcmfaces was to provide a unified framework that allows for analysis of earth variables on various grids. Fig. 2 shows four types of grids that are commonly used in ocean general circulation models (GCMs). Despite evident differences in GCM grid designs, such grids can all be represented as sets of connected arrays ('faces'). This fact is illustrated in Fig. 3 for the LLC90 grid (bottom right panel in Fig. 2) that is used in ECCO v4 (Forget et al., 2015).

The core of gcmfaces lies in its definition (in the '@gcmfaces/' subdi-50 rectory) of an additional Matlab data type ('class') that represents gridded 51 earth variables as sets of connected arrays. An object of the gcmfaces class 52 is stored in memory as shown in Table 1. The gcmfaces class inherits many 53 of its basic operations (e.g., +) from the 'double' class as illustrated by 54 **@gcmfaces/plus.m** in Table 2. Objects of the **gcmfaces** class can thus be 55 manipulated simply through compact and generic expressions such as 'a+b' 56 that are robust to changes in grid design (see section 3.3 for details). 57


Table 1: Gridded variable represented using the gcmfaces class. In this case the LLC90 grid (Fig. 2, bottom right) is used that has five faces (f1 to f5).

fld =		
	nFaces:	5
	f1:	[90x270 double]
	f2:	[90x270 double]
	f3:	[90x90 double]
	f4:	[270x90 double]
	f5:	[270x90 double]

Table 2: The '+' operation for gcmfaces objects (@gcmfaces/plus.m).

```
function r = plus(p,q)
%overloaded gcmfaces `+' function :
\% simply calls double `+' function for each face data
\% if any of the two arguments is a gcmfaces object
if isa(p,'gcmfaces'); r=p; else; r=q; end;
for iFace=1:r.nFaces;
   iF=num2str(iFace);
   if isa(p,'gcmfaces')&isa(q,'gcmfaces');
       eval(['r.f' iF '=p.f' iF '+q.f' iF ';']);
   elseif isa(p,'gcmfaces')&isa(q,'double');
       eval(['r.f' iF '=p.f' iF '+q;']);
   elseif isa(p,'double')&isa(q,'gcmfaces');
       eval(['r.f' iF '=p+q.f' iF ';']);
   else;
      error('gcmfaces plus: types are incompatible')
   end;
end;
```

Figure 3: Ocean topography displayed face by face for the LLC90 grid (Fig. 2, bottom right). The face indices (from 1 to 5) are overlaid in red. Within each face, grid point indices increase from left to right and bottom to top in this view that reflects the data organization in memory (Tab. 1). This plot is generated by calling 'example_display(1)'.



3 Basic Features

The representation of grid variables in memory is documented in section 3.1. Other key features of gcmfaces are 'exchange' functions that implement connections between faces (section 3.2) and 'overloaded' operations (section 3.3). I/O functions are discussed in section 3.4.

⁶³ 3.1 Grid Variables

In practice the gcmfaces framework gets activated by adding its directories to the Matlab path and loading a grid in memory using the grid_load.m function as done in sections 1.3. The default grid (LLC90) can be loaded in memory through a call to grid_load.m without any argument. For other grids, grid_load.m arguments need to be specified as explained by 'help grid_load.m'. grid_load.m stores all grid variables in memory within a global structure named mygrid (Tab.3).

mygrid can be accessed within Matlab at any point by declaring it as 'global mygrid;' or using gcmfaces_global.m. The latter method additionally: (1) issues a warning when 'mygrid has not yet been loaded to memory'; provides a few environment variables via myenv; adds gcmfaces directories to the path if needed. It should be stressed that gcmfaces functions often rely on mygrid and myenv. If they get deleted from memory (e.g., by a 'clear all') then a call to grid_load.m will re-activate gcmfaces properly.

The C-grid variable names listed in Tab.3 follow the MITgcm naming convention (see sections 2.11 and 6.2.4 in the MITgcm documentation⁴). In brief, XC, YC and RC denote longitude, latitude and vertical position of tracer variables. DXC, DYC, DRC and RAC are the corresponding grid spacings (in m) and grid cell areas (in m²). Another set of such fields (XG,

⁴http://mitgcm.org/public/r2_manual/latest/online_documents/manual.pdf

Table 3: List of grid variables contained in the mygrid global structure. The naming convention are directly inherited from the MITgcm. For details, see: http://mitgcm.org/public/r2_manual/latest/online_documents/manual.pdf

XC	:	[1x1 gcmfaces]	longitude (tracer)
YC	:	[1x1 gcmfaces]	latitude (tracer)
RC	:	[50x1 double]	depth (tracer)
XG	:	[1x1 gcmfaces]	longitude (vorticity)
YG	:	[1x1 gcmfaces]	latitude (vorticity)
RF	:	[51x1 double]	depth (velocity along 3rd dim)
DXC	:	[1x1 gcmfaces]	grid spacing (tracer, 1st dim)
DYC	:	[1x1 gcmfaces]	grid spacing (tracer, 2nd dim)
DRC	:	[50x1 double]	grid spacing (tracer, 3nd dim)
RAC	:	[1x1 gcmfaces]	grid cell area (tracer)
DXG	:	[1x1 gcmfaces]	grid spacing (vorticity, 1st dim)
DYG	:	[1x1 gcmfaces]	grid spacing (vorticity, 2nd dim)
DRF	:	[50x1 double]	grid spacing (velocity, 3nd dim)
RAZ	:	[1x1 gcmfaces]	grid cell area (vorticity)
AngleCS	:	[1x1 gcmfaces]	grid orientation (tracer, cosine)
AngleSN	:	[1x1 gcmfaces]	grid orientation (tracer, cosine)
Depth	:	[1x1 gcmfaces]	ocean bottom depth (tracer)
hFacC	:	[1x1 gcmfaces]	partial cell factor (tracer)
hFacS	:	[1x1 gcmfaces]	partial cell factor (velocity, 2nd dim)
hFacW	:	[1x1 gcmfaces]	partial cell factor (velocity, 1rst dim)

YG, RF, DXG, DYG, DRF, RAZ) is necessary to complete the C-grid spec-83 ification where velocity variables are shifted compared with tracer variables. 84 The indexing and vector conventions also derive from the MITgcm. The 85 indexing convention is illustrated for the LLC90 grid in Fig. 3. For a vector 86 field the first component (U) points straight to the right of the page in Fig. 3, 87 whereas the second component (V) points strait to the top of the page. The 88 location of U components are shifted by half a grid point towards the left of 89 the page, while the location of V components are shifted by half a grid point 90 towards the bottom of the page (reflecting the C-grid approach). 91

92 3.2 Exchange Functions

Many quantities of interest (e.g., gradients and flow convergences) involve 93 values from neighboring grid points that often need to be 'exchanged' between 94 faces. This is achieved in practice by appending rows and columns at the 95 sides of each face that are obtained from the neighboring faces – appending 96 rows and columns from faces #2, #3, and #5 at the sides of face #1 in the 97 Fig. 3 example. These exchanges are operated by exch_T_N.m for tracer 98 fields and by exch_UV_N.m for velocity fields. These functions are needed for 99 example to compute gradients (with calc_T_grad.m) and flow convergences 100 (with calc_UV_conv.m) in sections 4 and 5. 101

¹⁰² 3.3 Overloaded Functions

Table 2 depicts the overloading of the '+' operation by @gcmfaces/plus.m . In executing commands such as 'fld+1', Matlab will select @gcmfaces/plus.m if one of the arguments of '+' is of the gcmfaces class. Many common operations and functions are similarly overloaded in the '@gcmfaces/' directory that defines the gcmfaces class and its operations:

108 1. Logical operators: and, eq, ge, gt, isnan, le, lt, ne, not, or

Numerical operators: abs, angle, cat, cos, cumsum, diff, exp, imag,
log2, max, mean, median, min, minus, mrdivide, mtimes, nanmax,
nanmean, nanmedian, nanmin, nanstd, nansum, plus, power, rdivide,
real, sin, sqrt, std, sum, tan, times, uminus, uplus.

¹¹³ 3. Indexing operators: subsasgn, subsref, find, get, set, squeeze, repmat.

It is worth mentioning the case of **@gcmfaces/subsasgn.m** (subscripted assignment) and **@gcmfaces/subsref.m** (subscripted reference) since they are some of the most commonly used Matlab functions. For example, if fld is of the 'double' class then 'tmp2=fld(1);' and 'fld(1)=1;' respectively call subsref.m and subsasgn.m. If fld instead is of the **gcmfaces** class then **@gcmfaces/subsref.m** behaves as follows:

120 fld{n} returns the n[{]th} face data (i.e. an array).

121 fld(:,:,n) returns the n^{th} vertical level (i.e. a gcmfaces).

And **@gcmfaces/subsasgn.m** behaves similarly but for assignments. The variables in Table 1 can also be accessed 'manually'. For example:

124 fld.nFaces returns the nFaces attribute (double).

125 fld.f1 returns the face #1 array (double).

126 3.4 I/O Functions

Objects of the gcmfaces class can simply be saved to or read from file in Matlab's own I/O format ('.mat' files). An alternative is to use convert2array.m or convert2gcmfaces.m to re-organize the faces data into one array (or vice versa) that can readily be written to or read from binary files. The other file formats that are currently supported in the gcmfaces framework are: (1) the MITgcm 'mds' binary format documented here⁵; (2) the 'nctiles' format used to distribute ECCO v4 fields (Forget et al., 2015). When reading

⁵http://mitgcm.org/public/r2_manual/latest/online_documents/manual.pdf

¹³⁴ such files, the provided I/O functions (rdmds2gcmfaces.m, read_bin.m, and ¹³⁵ read_nctiles.m) reformat the data into gcmfaces objects on the fly.

136 4 Tutorial

Here it is assumed that the user has completed the installation procedure in
section 1.3 (including the installation of 'nctiles_climatology/' and 'm_map/').
gcmfaces_demo.m can then be executed by starting Matlab and typing

```
140 p = genpath('gcmfaces/'); addpath(p);
```

```
141 p = genpath('m_map/'); addpath(p);
```

```
142 gcmfaces_demo;
```

to illustrate several gcmfaces' capabilities. As prompted by gcmfaces_demo.m
the user specifies a desired amount of explanatory text output. gcmfaces_demo.m
then proceeds through the examples while displaying explanations in the
Matlab command window. Before each example the user is prompted to
type the return key to proceed further. The Matlab GUI and debugger can
also be used to run the examples line by line.

The first section of gcmfaces_demo.m illustrates I/O (grid_load.m 149) and plotting (example_display.m) capabilities. gcmfaces relies on 150 m_map (https://www.eoas.ubc.ca/ rich/map.html) for geographical projec-151 tions through the m_map_gcmfaces front-end that typically produces Fig. 4. 152 The convert2pcol function provides an alternative way to display results 153 directly via 'pcolor' (Fig. 5). The second section of gcmfaces_demo.m fo-154 cuses on data processing capabilities such as interpolation (example_interp.m 155) and smoothing (example_smooth.m). example_interp.m illustrates the 156 interpolation of gcmfaces fields to a lat-lon grid, and vice versa. example_smooth.m 157 integrates a diffusion equation, which illustrates computations of tracer gra-158 dients and flux convergences. Finally gcmfaces_demo.m illustrates compu-159






Figure 4: Same as Fig. 3 but plotted in geographical coordinates using m_map_gcmfaces.m. This plot is generated by calling 'example_display(4)'.




Figure 5: Same as Fig. 3 but plotted in geographical coordinates using convert2pcol.m. This plot is generated by calling 'example_display(3)'.

¹⁶¹ 5 Standard Analysis

The gcmfaces 'standard analysis' consists of an extensive set of physical di-162 agnostics that are routinely monitored in MITgcm simulations and ECCO v4 163 estimates (e.g., Forget et al., 2015, 2016). The computational loop is oper-164 ated by diags_driver.m that expects the data organization shown in Fig. 1. 165 The results of diags_driver.m are stored in a dedicated directory ('mat/' 166 in Fig. 1). The display phase is done afterwards by calling diags_display.m 167 (simple display to screen) or diags_driver_tex.m (to generate a tex file). 168 Here it is assumed that the user has completed the installation proce-169 dure in section 1.3 (including the installation of 'nctiles_climatology/' and 170 'm_map/'). The code below then generates and displays mean and vari-171 ance maps (setDiags='B' encoded in diags_set_B.m) from the ECCO v4 172 monthly mean climatology (12 monthly fields), which takes ≈ 5 minutes: 173

```
174 %add paths:
```

```
175 p = genpath('gcmfaces/'); addpath(p);
```

```
176 p = genpath('MITprof/'); addpath(p);
```

```
177 p = genpath('m_map/'); addpath(p);
```

```
178
```

179 %compute diagnostics:

```
180 help diags_driver;
```

```
181 dirModel='release2_climatology/';
```

```
182 dirMat=[dirModel 'mat/'];
```

```
183 setDiags='B';
```

```
184 diags_driver(dirModel,dirMat,'climatology',setDiags);
```

```
185
```

```
186 %display results:
```

```
187 diags_display(dirMat,setDiags);
```

Each generated plot has a caption that indicates the quantity being displayed. Other sets of diagnostic can be displayed similarly with different specifications of setDiags. Each one requires a specific set of model output. Sets of diagnostics that can be generated using 'nctiles_climatology/' or 'nctiles_monthly/' include oceanic transports ('A'), mean and variance maps ('B'), sections and time series ('C'), and mixed layer depths ('MLD').

If the 'setDiags' argument to diags_driver.m is omitted then these four diagnostic sets are generated at once, which takes $\approx 1/2$ hour. Each set of diagnostics (computation and display) is encoded in one routine with a name such as 'diags_set_XX.m' (where 'XX' stands for e.g., 'A', 'B', 'C', or 'MLD'). These routines can be found in the 'gcmfaces_diags/' subdirectory and are expected to be operated via diags_driver.m.

The results generated via diags_driver.m can then be displayed via diags_driver_tex.m which saves plots to disk and creates a compilable tex file including all of the plots. This can take an additional 10 minutes:

```
203 dirModel='release2_climatology/'; dirMat=[dirModel 'mat/'];
204 dirTex=[dirModel 'tex/']; nameTex='standardAnalysis';
205 diags_driver_tex(dirMat,{},dirTex,nameTex);
```

These same diagnostics can be generated for the monthly ECCO v4 time series (see Sect. 1.3 and Fig. 1) by setting 'dirModel' to 'release2/' in the above code snippet and changing the 'diags_driver.m' call to:

209 diags_driver(dirModel,dirMat,[1992:2011]);

Since the 20 year time series consists of 240 monthly records, computational times reported above are then multiplied by 20. The full computation therefore typically runs overnight. To speed up the process it can be distributed over multiple processors by splitting [1992:2011] into subsets.